

**Reissued: 01-Jul-11**

Model: ELP NX	Date: 06-Jul-09	No.: RD490002e
---------------	-----------------	----------------

**RTB Reissue**

The items in bold italics have been corrected.

Subject: Release Note: ELP NX		Prepared by: T.Nihei	
From: 1st Overseas Tech Support Sec., 1st PQM Dept.			
Classification:	<input type="checkbox"/> Troubleshooting	<input type="checkbox"/> Part information	<input type="checkbox"/> Action required
	<input type="checkbox"/> Mechanical	<input type="checkbox"/> Electrical	<input type="checkbox"/> Service manual revision
	<input type="checkbox"/> Paper path	<input type="checkbox"/> Transmit/receive	<input type="checkbox"/> Retrofit information
	<input type="checkbox"/> Product Safety	<input checked="" type="checkbox"/> Other (Firmware)	<input checked="" type="checkbox"/> Tier 2

This RTB has been issued to announce the firmware release information for the **ELP NX** (for 4 line LCD models).

<b>Version</b>	<b>Program No.</b>	<b>Effective Date</b>
<b><i>1.4.4.0-01</i></b>	<b><i>D4901401E</i></b>	<b><i>May 2011 production</i></b>
1.4.3.0-01	D4901401D	February 2011 production
1.4.1.0-01	D4901401C	August 2010 production
1.4.0.0-01	D4901401B	April 2010 production
1.3.1.0-01	D4901401A	August 2009 production
1.3.0.0-01	D4901401	1st Mass production

Reissued: 01-Jul-11

Model: ELP NX	Date: 06-Jul-09	No.: RD490002e
---------------	-----------------	----------------

Version	Modified Points or Symptom Corrected																																																			
1.4.4.0-01	<p><b>Other changes:</b></p> <p>1. <i>Support for Model DI-C1.5(D104/D106) has been added.</i></p> <p><b>Note: Requires the following Java VM firmware versions (or later):</b></p> <table border="1"> <thead> <tr> <th>GW Ver.</th> <th>Model name</th> <th>VM version</th> </tr> </thead> <tbody> <tr> <td rowspan="6">07A</td> <td>D017/D018/D019/D020</td> <td>4.16 or later</td> </tr> <tr> <td>D009/D011/D012/D013</td> <td>4.16 or later</td> </tr> <tr> <td>D014/D015</td> <td>4.16 or later</td> </tr> <tr> <td>G179</td> <td>4.16 or later</td> </tr> <tr> <td>D084/D085</td> <td>4.18 or later</td> </tr> <tr> <td>D091/D092</td> <td>4.18 or later</td> </tr> <tr> <td rowspan="4">08S</td> <td>D023/D025</td> <td>4.16 or later</td> </tr> <tr> <td>D027/D029</td> <td>4.16 or later</td> </tr> <tr> <td>D038/D041</td> <td>4.16 or later</td> </tr> <tr> <td>G190</td> <td>4.16 or later</td> </tr> <tr> <td rowspan="2">08A</td> <td>D062/D063/D065/D066</td> <td>5.05 or later</td> </tr> <tr> <td>G188/G189</td> <td>5.05 or later</td> </tr> <tr> <td rowspan="3">09S</td> <td>D067/D068/D069/D072</td> <td>6.04 or later</td> </tr> <tr> <td>M047</td> <td>5.07 or later</td> </tr> <tr> <td>D115/D116</td> <td>6.07 or later</td> </tr> <tr> <td rowspan="5">09A</td> <td>D081/D082</td> <td>7.01 or later</td> </tr> <tr> <td>M065/M066</td> <td>7.06 or later</td> </tr> <tr> <td>D088/D089</td> <td>7.06 or later</td> </tr> <tr> <td>D086/D087</td> <td>7.06 or later</td> </tr> <tr> <td>M022/M024/M026/M028</td> <td>7.09 or later</td> </tr> <tr> <td></td> <td>D104/D106</td> <td>7.09 or later</td> </tr> </tbody> </table>	GW Ver.	Model name	VM version	07A	D017/D018/D019/D020	4.16 or later	D009/D011/D012/D013	4.16 or later	D014/D015	4.16 or later	G179	4.16 or later	D084/D085	4.18 or later	D091/D092	4.18 or later	08S	D023/D025	4.16 or later	D027/D029	4.16 or later	D038/D041	4.16 or later	G190	4.16 or later	08A	D062/D063/D065/D066	5.05 or later	G188/G189	5.05 or later	09S	D067/D068/D069/D072	6.04 or later	M047	5.07 or later	D115/D116	6.07 or later	09A	D081/D082	7.01 or later	M065/M066	7.06 or later	D088/D089	7.06 or later	D086/D087	7.06 or later	M022/M024/M026/M028	7.09 or later		D104/D106	7.09 or later
GW Ver.	Model name	VM version																																																		
07A	D017/D018/D019/D020	4.16 or later																																																		
	D009/D011/D012/D013	4.16 or later																																																		
	D014/D015	4.16 or later																																																		
	G179	4.16 or later																																																		
	D084/D085	4.18 or later																																																		
	D091/D092	4.18 or later																																																		
08S	D023/D025	4.16 or later																																																		
	D027/D029	4.16 or later																																																		
	D038/D041	4.16 or later																																																		
	G190	4.16 or later																																																		
08A	D062/D063/D065/D066	5.05 or later																																																		
	G188/G189	5.05 or later																																																		
09S	D067/D068/D069/D072	6.04 or later																																																		
	M047	5.07 or later																																																		
	D115/D116	6.07 or later																																																		
09A	D081/D082	7.01 or later																																																		
	M065/M066	7.06 or later																																																		
	D088/D089	7.06 or later																																																		
	D086/D087	7.06 or later																																																		
	M022/M024/M026/M028	7.09 or later																																																		
	D104/D106	7.09 or later																																																		
1.4.3.0-01	<p>Other changes:</p> <p>1. Model S-C4.5(D115/D116) is now supported.</p>																																																			
1.4.1.0-01	<p>Other changes:</p> <p>1. Model Z-P1(M065/M066) is now supported.</p>																																																			
1.4.0.0-01	<p>Other changes:</p> <p>1. Support for Normal Print Jobs.</p> <p>2. Capital or lower case conversion can be selected.</p> <p>3. Up to 3 ELP-NX FS can be registered with 1 ELP-NX.</p>																																																			
1.3.1.0-01	<p>Symptom corrected:</p> <p>1. The "Non Locked Print Jobs" setting is returned default value (disable) after the power cycles though this setting is changed to enable.</p>																																																			
1.3.0.0-01	<p>1st Mass production</p> <p>Effected Models</p> <p>- S-C4 (D067/D068/D069/D072)</p>																																																			

**Reissued: 01-Jul-11**

Model: ELP NX	Date: 06-Jul-09	No.: RD490003d
---------------	-----------------	----------------

**RTB Reissue**

The items in bold italics have been added.

Subject: Release Note: ELP NX		Prepared by: T. Nihei	
From: 1st Overseas Tech Support Sec., 1st PQM Dept.			
Classification:	<input type="checkbox"/> Troubleshooting	<input type="checkbox"/> Part information	<input type="checkbox"/> Action required
	<input type="checkbox"/> Mechanical	<input type="checkbox"/> Electrical	<input type="checkbox"/> Service manual revision
	<input type="checkbox"/> Paper path	<input type="checkbox"/> Transmit/receive	<input type="checkbox"/> Retrofit information
	<input type="checkbox"/> Product Safety	<input checked="" type="checkbox"/> Other (Firmware)	<input checked="" type="checkbox"/> Tier 2

This RTB has been issued to announce the firmware release information for the **ELP NX** ( for Printer models).

<b>Version</b>	<b>Program No.</b>	<b>Effective Date</b>
<b><i>1.4.4.0-01</i></b>	<b><i>D4901701D</i></b>	<b><i>May 2011 production</i></b>
1.4.0.0-01	D4901701B	April 2010 production
1.3.1.0-01	D4901701A	August 2009 production
1.3.0.0-01	D4901701	1st Mass production

Reissued: 01-Jul-11

Model: ELP NX	Date: 06-Jul-09	No.: RD490003d
---------------	-----------------	----------------

Version	Modified Points or Symptom Corrected																																																			
1.4.4.0-01	<p><b>Other changes:</b></p> <ol style="list-style-type: none"> <li>Support for Model DI-C1.5(D104/D106) has been added.</li> </ol> <p><b>Note: Requires the following Java VM firmware versions (or later):</b></p> <table border="1"> <thead> <tr> <th>GW Ver.</th> <th>Model name</th> <th>VM version</th> </tr> </thead> <tbody> <tr> <td rowspan="6">07A</td> <td>D017/D018/D019/D020</td> <td>4.16 or later</td> </tr> <tr> <td>D009/D011/D012/D013</td> <td>4.16 or later</td> </tr> <tr> <td>D014/D015</td> <td>4.16 or later</td> </tr> <tr> <td>G179</td> <td>4.16 or later</td> </tr> <tr> <td>D084/D085</td> <td>4.18 or later</td> </tr> <tr> <td>D091/D092</td> <td>4.18 or later</td> </tr> <tr> <td rowspan="4">08S</td> <td>D023/D025</td> <td>4.16 or later</td> </tr> <tr> <td>D027/D029</td> <td>4.16 or later</td> </tr> <tr> <td>D038/D041</td> <td>4.16 or later</td> </tr> <tr> <td>G190</td> <td>4.16 or later</td> </tr> <tr> <td rowspan="2">08A</td> <td>D062/D063/D065/D066</td> <td>5.05 or later</td> </tr> <tr> <td>G188/G189</td> <td>5.05 or later</td> </tr> <tr> <td rowspan="3">09S</td> <td>D067/D068/D069/D072</td> <td>6.04 or later</td> </tr> <tr> <td>M047</td> <td>5.07 or later</td> </tr> <tr> <td>D115/D116</td> <td>6.07 or later</td> </tr> <tr> <td rowspan="5">09A</td> <td>D081/D082</td> <td>7.01 or later</td> </tr> <tr> <td>M065/M066</td> <td>7.06 or later</td> </tr> <tr> <td>D088/D089</td> <td>7.06 or later</td> </tr> <tr> <td>D086/D087</td> <td>7.06 or later</td> </tr> <tr> <td>M022/M024/M026/M028</td> <td>7.09 or later</td> </tr> <tr> <td></td> <td>D104/D106</td> <td>7.09 or later</td> </tr> </tbody> </table>	GW Ver.	Model name	VM version	07A	D017/D018/D019/D020	4.16 or later	D009/D011/D012/D013	4.16 or later	D014/D015	4.16 or later	G179	4.16 or later	D084/D085	4.18 or later	D091/D092	4.18 or later	08S	D023/D025	4.16 or later	D027/D029	4.16 or later	D038/D041	4.16 or later	G190	4.16 or later	08A	D062/D063/D065/D066	5.05 or later	G188/G189	5.05 or later	09S	D067/D068/D069/D072	6.04 or later	M047	5.07 or later	D115/D116	6.07 or later	09A	D081/D082	7.01 or later	M065/M066	7.06 or later	D088/D089	7.06 or later	D086/D087	7.06 or later	M022/M024/M026/M028	7.09 or later		D104/D106	7.09 or later
GW Ver.	Model name	VM version																																																		
07A	D017/D018/D019/D020	4.16 or later																																																		
	D009/D011/D012/D013	4.16 or later																																																		
	D014/D015	4.16 or later																																																		
	G179	4.16 or later																																																		
	D084/D085	4.18 or later																																																		
	D091/D092	4.18 or later																																																		
08S	D023/D025	4.16 or later																																																		
	D027/D029	4.16 or later																																																		
	D038/D041	4.16 or later																																																		
	G190	4.16 or later																																																		
08A	D062/D063/D065/D066	5.05 or later																																																		
	G188/G189	5.05 or later																																																		
09S	D067/D068/D069/D072	6.04 or later																																																		
	M047	5.07 or later																																																		
	D115/D116	6.07 or later																																																		
09A	D081/D082	7.01 or later																																																		
	M065/M066	7.06 or later																																																		
	D088/D089	7.06 or later																																																		
	D086/D087	7.06 or later																																																		
	M022/M024/M026/M028	7.09 or later																																																		
	D104/D106	7.09 or later																																																		
1.4.0.0-01	<p><b>Other changes:</b></p> <ol style="list-style-type: none"> <li>Model Kr-P2(M047) is now supported.</li> <li>Support for Normal Print Jobs.</li> <li>Capital or lower case conversion can be selected.</li> <li>Up to 3 ELP-NX FS can be registered with 1 ELP-NX.</li> </ol>																																																			
1.3.1.0-01	<p><b>Symptom corrected:</b></p> <ol style="list-style-type: none"> <li>The "Non Locked Print Jobs" setting is returned default value (disable) after the power cycles though this setting is changed to enable.</li> </ol>																																																			
1.3.0.0-01	<p>1st Mass production</p> <p>Effected Models</p> <ul style="list-style-type: none"> <li>- AI-P1(G179)</li> <li>- AP-P2(G188/G189)</li> <li>- G-P3(G190)</li> </ul> <p><b>Other changes:</b></p> <ul style="list-style-type: none"> <li>- ELP-NX now supports ELP-NX FS.</li> <li>- The Card Authentication Package is now optional if using ELP-NX.</li> <li>- The PS driver can now send Locked Print jobs to ELP-NX.</li> </ul>																																																			

Reissued: 25-Nov-11

Model: ELP NX	Date: 02-Jul-10	No.: RD490004b
---------------	-----------------	----------------

**RTB Reissue**

The items in bold italics have been corrected.

Subject: Release Note: ELP NX update module for Lapnet		Prepared by: T. Nihei	
From: 2nd Tech Service Sect., MFP/Printer Tech Service Dept.			
Classification:	<input type="checkbox"/> Troubleshooting	<input type="checkbox"/> Part information	<input type="checkbox"/> Action required
	<input type="checkbox"/> Mechanical	<input type="checkbox"/> Electrical	<input type="checkbox"/> Service manual revision
	<input type="checkbox"/> Paper path	<input type="checkbox"/> Transmit/receive	<input type="checkbox"/> Retrofit information
	<input type="checkbox"/> Product Safety	<input checked="" type="checkbox"/> Other (Firmware)	<input checked="" type="checkbox"/> Tier 2

This RTB has been issued to announce the firmware release information for the **ELP NX update module for Lapnet**.

Version	Program No.	Effective Date
<b><i>1.4.6.0-01</i></b>	<b><i>D4905101D</i></b>	<b><i>November 2011 production</i></b>
1.4.4.0-01	D4905101B	May 2011 production
1.4.0.0-01	D4905101A	June 2010 production
1.3.1.0-01	D4905101	June 2010 production

Version	Modified Points or Symptom Corrected
<b><i>1.4.6.0-01</i></b>	<p><b><i>Supported:</i></b>  <b><i>Support for the following devices has been added:</i></b>  <b><i>Sh-MF1 (M052/M053/M054)</i></b>  <b><i>OR-C1 (D120/D121/D122/D139/D140/D141)</i></b>  <b><i>Sh-P1 (M020/M021)</i></b>  <b><i>S-P3 (M080)</i></b></p> <p><b><i>Fixed:</i></b></p> <ol style="list-style-type: none"> <li><b><i>ELP-NX displays incorrect messages for the "Printing..." and "Deleting..." dialog boxes when using a non-English language on a 4-line LCD device.</i></b></li> <li><b><i>ELP-NX does not close the Deletion Confirmation Dialog if a user logs out from the device while the Deletion Confirmation Dialog is being displayed on a 4-line LCD device.</i></b></li> <li><b><i>Print jobs sent via the dedicated PS driver for some devices are not stored in the ELP-NX without CAP environment.</i></b></li> </ol> <p><b><i>Update the Java VM to the latest version before installing this update.</i></b></p>
1.4.4.0-01	<p>Other changes:</p> <ol style="list-style-type: none"> <li>Support for Model DI-C1.5 (D104/D106) has been added.</li> </ol>

Reissued: 25-Nov-11

Model: ELP NX	Date: 02-Jul-10	No.: RD490004b
---------------	-----------------	----------------

Version	Modified Points or Symptom Corrected
1.4.0.0-01	Other changes: <ol style="list-style-type: none"><li>1. Model R-C5.5(D084/D085) / Model AL-C1.5(D091/D092) / Model V-C3 (D081/D082) / Model Kr-P2(M047) are now supported.</li><li>2. Support for Normal Print Jobs.</li><li>3. Capital or lower case conversion can be selected.</li><li>4. Up to 3 ELP-NX FS can be registered with 1 ELP-NX.</li></ol>
1.3.1.0-01	Other changes: <ol style="list-style-type: none"><li>1. Model AL-P1(G179) / Model G-P3(G190) / Model AP-P2(G188/G189) / Model S-C4(D067/D068/D069/D072) are now supported.</li><li>2. ELP-NX now supports ELP-NX FS.</li><li>3. The Card Authentication Package is now optional if using ELP-NX.</li><li>4. The PS driver can now send Locked Print jobs to ELP-NX.</li></ol>

**Reissued: 02-Jul-12**

Model: ELP NX	Date: 19-Nov-08	No.: RD490001k
---------------	-----------------	----------------

**RTB Reissue**

The items in bold italics have been corrected.

Subject: Release Note: ELP NX		Prepared by: S. Maruyama	
From: 1st Solution Support Sect., Solution Support Dept.			
Classification:	<input type="checkbox"/> Troubleshooting	<input type="checkbox"/> Part information	<input type="checkbox"/> Action required
	<input type="checkbox"/> Mechanical	<input type="checkbox"/> Electrical	<input type="checkbox"/> Service manual revision
	<input type="checkbox"/> Paper path	<input type="checkbox"/> Transmit/receive	<input type="checkbox"/> Retrofit information
	<input type="checkbox"/> Product Safety	<input checked="" type="checkbox"/> Other (Firmware)	<input checked="" type="checkbox"/> Tier 2

This RTB has been issued to announce the firmware release information for the **ELP NX**.

Version	Program No.	Effective Date	Availability of RFU
<b>1.4.8.0-01</b>	<b>D4900001M</b>	<b>June 2012 production</b>	<b>Not available</b>
1.4.7.0-01	D4900001L	June 2012 production	Not available
1.4.6.0-01	D4900001K	November 2011 production	Not available
1.4.4.0-01	D4900001I	May 2011 production	Not available
1.4.3.0-01	D4900001H	February 2011 production	Not available
1.4.2.0-01	D4900001G	November 2010 production	Not available
1.4.1.0-01	D4900001F	August 2010 production	Not available
1.4.0.0-01	D4900001E	April 2010 production	Not available
1.3.1.0-01	D4900001D	August 2009 production	Not available
1.3.0.0-01	D4900001C	July 2009 production	Not available
1.2.0.0-01	D4900001B	April 2009 production	Not available
1.10a	D4900001A	1st Mass production	Not available

**Note: Definition of Availability of RFU via @Remote**

**“Available”** The firmware can be updated via RFU or SD card.

**“Not available”**: The firmware can only be updated via SD card.

Version	Modified Points or Symptom Corrected
<b>1.4.8.0-01</b>	<p><b>Supported:</b>  <b>Support for the following devices has been added:</b>  <b>MT-C5</b>  <b>GR-C1</b>  <b>S-C5</b></p> <p><b>Update the Java VM to the latest version before installing this update.</b></p>
1.4.7.0-01	<p>Supported:  Support for the following devices has been added:  AP-C3  AT-C3  AL-C2</p>
1.4.6.0-01	<p>Supported:  Support for the following devices has been added:  Sh-MF1 (M052/M053/M054)  OR-C1 (D120/D121/D122/D139/D140/D141)  Sh-P1 (M020/M021)  S-P3 (M080)</p>

**Reissued: 02-Jul-12**

Model: ELP NX	Date: 19-Nov-08	No.: RD490001k
---------------	-----------------	----------------

Version	Modified Points or Symptom Corrected
	<p>Fixed:</p> <ol style="list-style-type: none"> <li>1. ELP-NX displays incorrect messages for the "Printing..." and "Deleting..." dialog boxes when using a non-English language on a 4-line LCD device.</li> <li>2. ELP-NX does not close the Deletion Confirmation Dialog if a user logs out from the device while the Deletion Confirmation Dialog is being displayed on a 4-line LCD device.</li> <li>3. Print jobs sent via the dedicated PS driver for some devices are not stored in the ELP-NX without CAP environment.</li> </ol>
1.4.4.0-01	<p>Other changes:</p> <ol style="list-style-type: none"> <li>1. Support for Model DI-C1.5 (D104/D106) has been added.</li> </ol>
1.4.3.0-01	<p>Other changes:</p> <ol style="list-style-type: none"> <li>1. Models Z-C1(M022/M024/M026/M028) and S-C4.5(D115/D116) are now supported.</li> </ol>
1.4.2.0-01	<p>Other changes:</p> <ol style="list-style-type: none"> <li>1. Models AT-C2.5(D086/D087) and AP-C2.5(D088/D089) are now supported.</li> <li>2. Simplified Chinese is now supported.</li> </ol>
1.4.1.0-01	<p>Other changes:</p> <ol style="list-style-type: none"> <li>1. Model Z-P1(M065/M066) is now supported.</li> </ol>
1.4.0.0-01	<p>Other changes:</p> <ol style="list-style-type: none"> <li>1. Model R-C5.5(D084/D085) / Model AL-C1.5(D091/D092) / Model V-C3 (D081/D082) / Model Kr-P2(M047) are now supported.</li> <li>2. Support for Normal Print Jobs.</li> <li>3. Capital or lower case conversion can be selected.</li> <li>4. Up to 3 ELP-NX FS can be registered with 1 ELP-NX.</li> </ol>
1.3.1.0-01	<p>Symptom corrected:</p> <ol style="list-style-type: none"> <li>1. The "Non Locked Print Jobs" setting is returned default value (disable) after the power cycles though this setting is changed to enable.</li> </ol>
1.3.0.0-01	<p>Other changes:</p> <ol style="list-style-type: none"> <li>1. Model AL-P1 / Model G-P3 / Model AP-P2 / Model S-C4 are now supported.</li> <li>2. ELP-NX now supports ELP-NX FS.</li> <li>3. The Card Authentication Package is now optional if using ELP-NX.</li> <li>4. The PS driver can now send Locked Print jobs to ELP-NX.</li> </ol>
1.2.0.0-01	<p>Other changes:</p> <ol style="list-style-type: none"> <li>1. Model AT-C2 / Model AP-C2 / Model DI-C1 / Model MT-C4 are now supported.</li> <li>2. Follow Me Printing is newly supported.</li> </ol>
1.10a	<p>Other changes:</p> <ol style="list-style-type: none"> <li>1. Model R-C5 / Model AL-C1 / Model V-C2 are supported.</li> <li>2. 1st Mass production</li> </ol>

Reissued: 02-Jul-12

Model: ELP NX	Date: 02-Jul-10	No.: RD490005d
---------------	-----------------	----------------

**RTB Reissue**

The items in bold italics have been corrected.

Subject: Release Note: ELP NX update module for Activation		Prepared by: S. Maruyama	
From: 1st Solution Support Sect., Solution Support Dept.			
Classification:	<input type="checkbox"/> Troubleshooting	<input type="checkbox"/> Part information	<input type="checkbox"/> Action required
	<input type="checkbox"/> Mechanical	<input type="checkbox"/> Electrical	<input type="checkbox"/> Service manual revision
	<input type="checkbox"/> Paper path	<input type="checkbox"/> Transmit/receive	<input type="checkbox"/> Retrofit information
	<input type="checkbox"/> Product Safety	<input checked="" type="checkbox"/> Other (Firmware)	<input checked="" type="checkbox"/> Tier 2

This RTB has been issued to announce the firmware release information for the **ELP NX update module for Activation**.

Version	Program No.	Effective Date	Availability of RFU
<b><i>1.4.8.0-01</i></b>	<b><i>D4905001E</i></b>	<b><i>June 2012 production</i></b>	<b><i>Not available</i></b>
1.4.7.0-01	D4905001D	June 2012 production	Not available
1.4.6.0-01	D4905001C	November 2011 production	Not available
1.4.4.0-01	D4905001A	May 2011 production	Not available
1.4.0.0-01	D4905001	June 2010 production	Not available

Note: Definition of Availability of RFU via @Remote

“Available” The firmware can be updated via RFU or SD card.

“Not available”: The firmware can only be updated via SD card.

Version	Modified Points or Symptom Corrected
<b><i>1.4.8.0-01</i></b>	<p><b><i>Supported:</i></b>  <b><i>Support for the following devices has been added:</i></b>  <b><i>MT-C5</i></b>  <b><i>GR-C1</i></b>  <b><i>S-C5</i></b></p> <p><b><i>Update the Java VM to the latest version before installing this update.</i></b></p>
1.4.7.0-01	<p>Supported:  Support for the following devices has been added:  AP-C3  AT-C3  AL-C2</p>
1.4.6.0-01	<p>Supported:  Support for the following devices has been added:  Sh-MF1 (M052/M053/M054)  OR-C1 (D120/D121/D122/D139/D140/D141)  Sh-P1 (M020/M021)  S-P3 (M080)</p> <p>Fixed:  1. ELP-NX displays incorrect messages for the "Printing..." and "Deleting..." dialog boxes when using a non-English language on a 4-line LCD device.  2. ELP-NX does not close the Deletion Confirmation Dialog if a user logs out</p>

Reissued: 02-Jul-12

Model: ELP NX	Date: 02-Jul-10	No.: RD490005d
---------------	-----------------	----------------

Version	Modified Points or Symptom Corrected
	from the device while the Deletion Confirmation Dialog is being displayed on a 4-line LCD device. 3. Print jobs sent via the dedicated PS driver for some devices are not stored in the ELP-NX without CAP environment.
1.4.4.0-01	Other changes: 1. Support for Model DI-C1.5 (D104/D106) has been added.
1.4.0.0-01	Other changes: 1. Model R-C5.5(D084/D085) / Model AL-C1.5(D091/D092) / Model V-C3 (D081/D082) / Model Kr-P2(M047) are now supported. 2. Support for Normal Print Jobs. 3. Capital or lower case conversion can be selected. 4. Up to 3 ELP-NX FS can be registered with 1 ELP-NX.