

=====
*** Basic Information ***
=====

[Create date] 2018/12/21

[Program Name] ADF_DF3090

[Version] 01.380:03

[PCB No.]

[Interchangeability] X / O

[Other Firmware Requirements] None

[PCB Requirements] None

[Software category] Normal Release

[Release category] Normal Release

[Program category] Firmware

Exported to(language) GEN(all)

[Firmware No.] D7795300Q

[File Information]

File Name D7795300Q.fwu

File Type Module for Service

Size 0.13 MB (132216 byte)

[Availability of RFU] No

[Production reflection] 2019/02

=====
*** Note ***
=====

[Note]

=====
*** Important Notes ***
=====

[Important Notes]

=====
*** Modification History ***
=====

[Modifications made:]

Rank C

Symptom corrected:
- SC702-03 might occur.

[Modification history]

Version 01.360:03
Rank D

Other changes:
- A minor change only for the Japanese model.

Version 01.350:03
Rank C

Other changes:
- When the solenoid stays on for five seconds, the system will be reset and the solenoid will be turned off.

Version 01.340:03
Rank C

Symptom corrected:
- SC701-08 might occur

Version 01.330:03
Symptom corrected:
- Initial Jam 001 might occur if another document is fed into the ADF while a single-sided document is being scanned.

Version 01.320:03
Other changes:
- The ON/OFF timing of the electromagnetic clutch was changed, to reduce the load on the drive motor.
- The range of detection of Jam 14: Skew Correction Sensor was changed, to reduce the occurrences of the jam.

Version 01.300:03
In the Administrator Tools tab in System Settings, "ADF operation: Copier/Document Server: Silent Mode" was added as a new option for another model.

Version 01.290:03
Symptom corrected:
- JAM01 or JAM16 may occur when scanning thin originals.
- JAM14 may occur as a result of an unwanted delay in feeding out the last sheet of the original.
- Lifting up the ADF during initialization may cause JAM14 in the process following the initialization.

Version 01.200:03

Specification Change:

Minor change in the administrative update process; no changes operational wise.

Version 01.130:03

Version number changed for version management purposes (No program changes made).

Version 01.090:02

Symptom corrected:

1. SC620 may occur.

Other changes:

2. Improved accuracy of paper alignment at paper exit.

Version 01.060:02

Symptom corrected:

Supports scanning of A6 sized originals.

Version 01.060:02

Symptom corrected:

Supports scanning of A6 sized originals.

Version 01.050:01

1st Mass production

