

Reissued: 20-Sep-16

Model: Internal Finisher SR3180	Date: 04-Dec-13	No.: RD766001f
---------------------------------	-----------------	----------------

**RTB Reissue**

 The items in ***bold italics*** have been added.

Subject: Firmware Release Note: Internal Finisher SR3180		Prepared by: R. Tsurumi	
From: 1st Tech Service Sect., MFP/Printer Tech Service Dept.			
Classification:	<input type="checkbox"/> Troubleshooting <input type="checkbox"/> Mechanical <input type="checkbox"/> Paper path <input type="checkbox"/> Product Safety	<input type="checkbox"/> Part information <input type="checkbox"/> Electrical <input type="checkbox"/> Transmit/receive <input checked="" type="checkbox"/> Other (Firmware)	<input type="checkbox"/> Action required <input type="checkbox"/> Service manual revision <input type="checkbox"/> Retrofit information <input checked="" type="checkbox"/> Tier 2

This RTB has been issued to announce the firmware release information for the **Internal Finisher SR3180**.

Version	Program No.	Effective Date	Availability of RFU
<b><i>01.160:05</i></b>	<b><i>D7665550L</i></b>	<b><i>November 2016 production</i></b>	<b><i>Not Available</i></b>
01.150:05	D7665550K	September 2015 production	Not Available
01.130:06	D7665550J	September 2014 production	Not Available
01.120:05	D7665550H	August 2014 production	Not Available
01.110:05	D7665550G	June 2014 production	Not Available
01.080:05	D7665550F	March 2014 production	Not Available
01.050:05	D7665550E	1st Mass production	Not Available

**Note: Definition of Availability of RFU via @Remote**
**"Available":** The firmware can be updated via RFU or SD card.

**"Not available":** The firmware can only be updated via SD card.

Version	Modified Points or Symptom Corrected
<b><i>01.160:05</i></b>	<b><i>Symptom corrected:</i></b> <b><i>- Minor bug correction</i></b>
01.150:05	Specification change: Support of "Oficio" paper  Symptom corrected: Staple-less stapling does not work correctly in low speed mode.
01.130:06	Symptom corrected 1. The shift motor becomes unsynchronized. 2. A software reset occurs.
01.120:05	Symptom corrected The paper full condition is detected too early.
01.110:05	Symptom corrected 1. Early "paper full" detection for the exit tray. 2. A jam occurs (Jam code 1, 302, 303, 308).
01.080:05	Other changes: Staple alignment was improved.
01.050:05	1st Mass production